


On the Admin account, right click on the Green Pilot Light symbol and select The UWF Configuration tool.

Logon: Admin


PW: Administrator

Logon: User



PW: User



If the Pilot Light symbol is missing from the task bar, the work around is to logout of Admin and login again. The password is Administrator.




The UWF dialogue window is shown below




To change state from either enable or disable mode, click on the change button. You will then be prompted to restart the client for the change to take effect and the Pilot Light symbol will come back in red.


Note the UWF must be in the disabled (red) state before you can make any changes and save them.




For Kiosk mode you want to have the thin client Auto logon to the User account. Selecting the Assign Auto Logon User button will present the above dialogue. The pull down in the Default User Name will give the option for Admin or User. It is suggested to deploy the thin client to users with the device Auto Logon set to User and the UWF in the enabled mode. This is the most locked down mode and prevents the unauthorized user from making changes to the thin client. The account credentials are at the top of this document.




To Set Up Kiosk Mode Select UWF Configuration Utility




Then select the Shell Launcher Tab



Click on the Change button to change state from Enable to Disable




After you have setup TermPro, right click on TermPro and select Properties




Then copy the Target string

Paste the target string in User Shell field




Type User in User in the User Account Name field



Then click on the Set Shell Button

The target string will move to the position shown below




The Restart shell radio button will restart the TermPro application, if the User exits out of the session.

This completes the Kiosk Mode set up.

Click on the X to close the dialogue and then click X again to completely close the UWF dialogue.


Now restart the thin client.

Your thin client should auto login to the User Account
Your TermPro session should auto launch as shown



Sign Out of the User account and login as Admin.

Select the UWF Configuration tool again and change state to the enabled state which is the recommended state to deploy the thin client for users is indicated by a green light. Reboot again and your TermPro session will launch again.



If you need to exit out of KIOSK mode type CTRL – ALT – Delete and perform a sign out or switch user to Admin in order to make changes.

A Video showing this process with the Chrome Browser is available at this link:
<https://www.youtube.com/watch?v=VzzODLJ5z9k&t=52s>

Download CLI’s Free Management Tool, DevMan, for installation on a PC or Server.
<https://computerlab.com/index.php/downloads/category/27-device-manager>

Contact CLI Technical Support with any questions at 1-800-727-5250 option 3, or click on this [Submit a SUPPORT Request](#) link. View CLI’s Support page for knowledge base articles, Firmware downloads and documentation at: <https://computerlab.com/index.php/support>